

Link Tender Drivers to Applicator - SKY Dispatch


Last Modified on 01/19/2026 10:05 am CST

This enhancement introduces the ability to create an optional link between a Tender Driver and an Applicator. When linked, all assignments made to the Applicator automatically mirror to the Tender Driver in the same job order. This workflow supports scenarios where a Tender Driver works directly with one Applicator throughout a day or season.

A Tender Driver's assignments cannot be edited or reordered while they are linked to an Applicator. A SKY account cannot be linked to itself, meaning a person cannot act as both the Applicator and Tender Driver for the same set of assignments. Linking is optional and is configured per Tender Driver.

Company Settings

Within *Company Settings*, the configuration for tender-related roles is found under the *Agvance Ops* tab.



Agvanc...	Applicator Alias	Vehicle	Sky Use...	Sky User Email	Map Icon	Update ...	Require...	Edit Tic...	Capture...	Choose ...
Joe Example	123ABC	Vehicle	Joe Example	Joe Example	✓	✗	✓	✗	✗	✗
Anna Admin	Applicator1	TerraGator Dry Spinner	Anna Admi...	Anna Admi...	✗	✓	✗	✓	✗	✓

- Tender Alias
- Vehicle
- Sky Username
- Sky User Email
- Link to Applicator
- Map Icon
- Vehicle Location
- Integration Type
- Machine Alias

The screenshot shows the Tender Setup grid in the Advance Sky Dispatch software. The grid lists tenders with the following columns: Tender Alias, Vehicle, Sky Username, Sky User Email, Link to Applicator, Map Icon, Vehicle Location, Integration Type, and Machine Alias. Filters are applied for Tender Alias (ER, JD), Vehicle (Case Floater Unit 150, Case IH 275 Unit 700), Sky Username (Emily, Joe Dev Example II), and Link to Applicator (None, Applicator). The grid shows two rows of data with icons for edit, delete, and details.

Tender Alias	Vehicle	Sky Username	Sky User Email	Link to Applicator	Map Icon	Vehicle Location	Integration Type	Machine Alias
ER	Case Floater Unit 150	Emily	emily.snowdon@example.com	None	佛陀	Vehicle Location	--	--
JD	Case IH 275 Unit 700	Joe Dev Example II	joe.dev.example@example.com	Applicator	佛陀	Vehicle Location	--	--

The *Tender Setup* grid supports the following actions:

- Establish links to Applicators
- Manage active links
- Remove links

Establishing a Link

When linking a Tender Driver to an Applicator:

- All current Applicator assignments are immediately added to the Tender Driver.
- Tender Driver must be unassigned from all jobs before linking to an Applicator.
- Removing the link will remove all assignments - there isn't an option to keep.

General **Apply** Custom Tags Integrations Vehicles

Tender Setup

Add, Edit, Update Permissions, and Deactivate Tenders

...

X 0 O 0 Export ...

Tender Alias	Vehicle	Sky Username	Sky User Email	Link to Applicator
ER	Case Floater Unit 150	Emily ...	emily ...	<input type="button" value="Filter"/> <div style="border: 1px solid #ccc; padding: 5px; display: inline-block;"> None ES KS </div>

You have 0 changes in this row

General **Apply** Custom Tags Integrations Vehicles

Tender Setup

Add, Edit, Update Permissions, and Deactivate Tenders

...

X 0 O 0 Export ...

Tender Alias	Vehicle	Sky Username	Sky User Email	Link to Applicator	Map Icon	Vehicle Location	Integration Type	Machine Alias
ER	Case Floater Unit 150	Emily ...	emily ...	<input type="button" value="Filter"/> <div style="border: 1px solid #ccc; padding: 5px; display: inline-block;"> None ES KS </div>

You have 0 changes in this row and 0 hidden columns

Cancel Done

Once the link is confirmed, all existing assignments for the Applicator are immediately added to the Tender Driver, and any new, updated, or removed assignments continue to mirror automatically. The Tender Driver's schedule always follows the same job order as the Applicator, and any changes made to the Applicator's schedule are reflected automatically.

Linking Behavior

Once the link is confirmed, the Tender Driver receives all current assignments from the Applicator, and any future assignment changes including reassignment, deletion, or job order adjustments automatically mirror to the Tender Driver. The Tender Driver's job order always matches the Applicator's job order and cannot be altered while linked.

Removing a Link

Removing a link clears all assignments from the Tender Driver. There is no option to keep assignments when the link is removed.

After unlinking, the Tender Driver may receive independent assignments again.

Multiple Tender Drivers

An Applicator may be linked to multiple Tender Drivers. Each linked Tender Driver receives the same assignments as the Applicator, and any schedule changes made to the Applicator update all linked Tender Drivers automatically.

Schedule

When a Tender Driver is linked to an Applicator, their schedule always matches the Applicator's. The Tender Driver's job cards cannot be moved or reordered while linked, and any changes made to the Applicator update the

Tender Driver automatically.