

Scale Ticket Level Management - Mass Edit Ownership Values Utility

Last Modified on 07/11/2025 1:18 pm CDT

The Mass Edit Ownership Values utility allows Scale Ticket split arrangements to be changed to a different split arrangement. At the same time the *Assembly #*, *Farm ID*, *Field ID*, *DPR*, *Shrink Schedule*, *Dock Schedule*, *Drying Schedule*, and *Freight Percent* can be changed.

Using the Mass Edit Ownership Utility

1. The utility is found at *Grain / Utilities / Mass Edit / Ownership Values*.
2. Select Scale Tickets to change the ownership. All selected Scale Tickets will have the same ownership change. Choose **Done** when all Scale Tickets are selected.
 - Use filters to help narrow the list of Scale Tickets.
 - Only Scale Tickets with the same *Commodity ID* should be selected.
3. The selected Scale Tickets are loaded into the top grid of the *Mass Edit Ownership* window.

The screenshot shows the 'Mass Edit Ownership' window. It features a table with columns: Assembly ID, Location ID, Commodity ID, <Ticket #>, Date, Farm Grower ID, Farm ID, Farm Description, Field Grower ID, Field ID, Field Description, and View Original Ticket. The table contains four rows of data. Below the table is a form with fields for <Assembly #>, <Farm ID>, <Field ID>, Location, Commodity, and Total Gross Units. There are buttons for 'Load Information', 'Remove Contracts from Selected Tickets', 'Save', and 'Cancel'.

	Assembly ID	Location ID	Commodity ID	<Ticket #>	Date	Farm Grower ID	Farm ID	Farm Description	Field Grower ID	Field ID	Field Description	View Original Ticket
1	48	00MAIN	Corn	5987	06/24/2024							View
2	51	00MAIN	Corn	8001	01/29/2024							View
3	51	00MAIN	Corn	8002	01/29/2024							View
4	51	00MAIN	Corn	8003	01/29/2024							View

☐ <Assembly #> 48 ? Location 00MAIN Commodity Corn Load Information

☐ <Farm ID> ☐ <Field ID>

Total Gross Units: 1112.9100 Remove Contracts from Selected Tickets

	<Customer ID>	Name	Share%	DPR	<Contract>	<Dock Schedule>	<Shrink Schedule>	Charge ID	<Drying Charge Schedule>	CondoYn	FreightPercent	Hold
1	237018	Abb...	100.00...	Pr		NOSCHEDULE	Store	No C...	Store	<input type="checkbox"/>	100.0000	<input type="checkbox"/>

Save Cancel

4. To load information into the bottom grid, highlight a Scale Ticket in the top grid and select **Load Information**.
 - a. Select the Scale Ticket that contains the information to populate on all other tickets by selecting the row to highlight it. If the same information should not be populated on multiple tickets, select any Scale Ticket.
 - b. Choose **View** to review the Scale Ticket information on the ticket before selecting it.
 - c. If an Assembly is selected, the default assembly split information will default into the bottom grid.
 - d. If a Farm is selected, the farm splits will default into the bottom grid.
5. Changing ownership on any selected Scale Tickets containing Purchase Contracts requires selecting **Remove Contracts from Selected Tickets**. This clears the contract(s) and applies the new contract information to the Scale Ticket.

6. Updating Scale Ticket information:

- An *Assembly #*, *Farm ID*, and *Field ID* can be changed on a Scale Ticket if the checkbox is selected.
 - If *Assembly #* is checked, the *Assembly #* must be for the same Commodity and Location.
- If no information defaults in the grid or if the defaulted information needs changed, double-click *Customer ID* to select the Customer(s) of the new split arrangement.
 - *Share%*, *DPR*, *Contract*, *Shrink Schedule*, *Charge ID* (Storage/Service charge), *Drying Charge Schedule*, and *Freight Percent* can be changed for the split arrangement.
 - Changing the *Charge ID* (Storage/Service Charge schedule) removes any pre-existing charges.

7. Once split arrangement information is set, choose **Save** to update the Scale Ticket(s) selected.