

Scale Ticket Level Management - Mass Edit Ownership Values Utility

Last Modified on 02/25/2022 3:23 pm CST

Overview

In Grain, there are two modes of operation: The Standard mode where Scale Tickets are directly associated to the Assembly, and Scale Ticket Level Management where Scale Tickets have an independent relationship to the Assembly. Setup for these two modes is inherently different and therefore they are not interchangeable within Grain.

The information listed in this document is specific to the Scale Ticket Level Management mode of operation.

The Mass Edit Ownership Values utility allows Scale Ticket split arrangements to be changed to a different split arrangement. At the same time the *Assembly #*, *Farm ID*, *Field ID*, *DPR*, *Shrink Schedule*, *Dock Schedule*, *Drying Schedule*, and *Freight Percent* can be changed.

Details

Using the Mass Edit Ownership Utility

1. The utility is found at *Grain / Utilities / Mass Edit / Ownership Values*.
2. Select Scale Tickets to change the ownership. All selected Scale Tickets will have the same ownership change. Choose **Done** when all Scale Tickets are selected.
 1. Use filters to help narrow the list of Scale Tickets.
 2. Only Scale Tickets with the same *Commodity ID* should be selected.
3. The selected Scale Tickets are loaded into the top grid of the *Mass Edit Ownership* window.

Mass Edit Ownership

	Assembly ID	Location ID	Commodity ID	<Ticket#>	Date	Farm Grower ID	Farm ID	Farm Description	Field Grower ID	Field ID	Field Description	View Original Ticket
1	6903	062	Corn	745896A	01/...	910563	TestAcct	Grain Testing F...				View
2	6904	062	Corn	694919	04/...	910563	TestAcct	Grain Testing F...				View
3	6904	062	Corn	4512365	05/...							View
4	6904	062	Corn	4875461	05/...							View
5	6905	062	Corn	694924	05/...							View

☐ <Assembly #> 6903 Location 062 Commodity Corn Load Information

☐ <Farm ID> TestAcct <Field ID> Remove Contracts from Selected Tickets

Total Gross Units: 9228.0900

	<Customer ID>	Name	Share%	DPR	<Contract>	<Dock Schedule>	<Shrink Schedule>	Charge ID	<Drying Charge Schedule>	CondoYn	Freight Percent
1	910563	GRAIN TESTING	100.0000	Priced	65271	NOSCHEDULE	C2	2018 Corn Storage	C1	<input type="checkbox"/>	100.0000

Save Cancel

4. To load information into the bottom grid, highlight a Scale Ticket in the top grid and select **Load Information**.

1. Select the Scale Ticket that contains the information to populate on all other tickets by clicking on the row to highlight it. If the same information should not be populated on multiple tickets, select any Scale Ticket.
2. Choose **View** to review the Scale Ticket information on the ticket before selecting it.
3. If an Assembly is selected the default assembly split information will default into the bottom grid.
4. If a Farm is selected the farm splits will default into the bottom grid.
5. Changing ownership on any selected Scale Tickets containing Purchase Contracts requires the use of **Remove Contracts from Selected Tickets**. This clears the contract(s) and applies the new contract information to the Scale Ticket.
6. Updating Scale Ticket information:
 1. An *Assembly #*, *Farm ID*, and *Field ID* can be changed on a Scale Ticket if the checkbox is selected.
 1. If *Assembly #* is checked, the *Assembly #* must be for the same *Commodity* and *Location*.
 2. If no information defaults in the grid or to change the defaulted information, double-click **Customer ID** to select the Customer(s) of the new split arrangement.
 1. *Share%*, *DPR*, *Contract*, *Shrink Schedule*, *Charge ID* (Storage/Service charge), *Drying Charge Schedule*, and *Freight Percent* can be changed for the split arrangement.
 2. Changing the *Charge ID* (Storage/Service Charge schedule) removes any pre-existing charge.
7. Once split arrangement information is set, choose **Save** to update the Scale Ticket(s) selected.

?