

Scale Ticket Level Management - Mass Edit Ownership Values Utility

Last Modified on 08/23/2024 10:01 am CDT

In Grain, there are two models of operation:

- The Standard model where Scale Tickets are directly associated to the Assembly
- Scale Ticket Level Management where Scale Tickets have an independent relationship to the Assembly.

Setup for these two models is inherently different and therefore not interchangeable within Grain.

The information in this article is specific to the Scale Ticket Level Management model.

The Mass Edit Ownership Values utility allows Scale Ticket split arrangements to be changed to a different split arrangement. At the same time the *Assembly #*, *Farm ID*, *Field ID*, *DPR*, *Shrink Schedule*, *Dock Schedule*, *Drying Schedule*, and *Freight Percent* can be changed.

Using the Mass Edit Ownership Utility

1. The utility is found at *Grain / Utilities / Mass Edit / Ownership Values*.
2. Select Scale Tickets to change the ownership. All selected Scale Tickets will have the same ownership change. Choose **Done** when all Scale Tickets are selected.
 - Use filters to help narrow the list of Scale Tickets.
 - Only Scale Tickets with the same *Commodity ID* should be selected.
3. The selected Scale Tickets are loaded into the top grid of the *Mass Edit Ownership* window.

	Assembly ID	Location ID	Commodity ID	<Ticket #	Date	Farm Grower ID	Farm ID	Farm Description	Field Grower ID	Field ID	Field Description	View Original Ticket
1	48	00MAIN	Corn	5987	08/24/2024							View
2	51	00MAIN	Corn	8001	01/29/2024							View
3	51	00MAIN	Corn	8002	01/29/2024							View
4	51	00MAIN	Corn	8003	01/29/2024							View

<Assembly # 48 ? Location 00MAIN Commodity Corn Load Information

<Farm ID <Field ID

Total Gross Units: 1112.9100 Remove Contracts from Selected Tickets

	<Customer ID	Name	Share%	DPR	<Contract	<Dock Schedule	<Shrink Schedule	Charge ID	<Drying Charge Schedule	Condo Yn	Freight Percent	Hold
1	237018	Abb...	100.00...	Pr		NOSCHEDULE	Store	No C...	Store	<input type="checkbox"/>	100.0000	<input type="checkbox"/>

Save Cancel

4. To load information into the bottom grid, highlight a Scale Ticket in the top grid and select **Load Information**.
 - a. Select the Scale Ticket that contains the information to populate on all other tickets by selecting the row to highlight it. If the same information should not be populated on multiple tickets, select any Scale

Ticket.

- b. Choose **View** to review the Scale Ticket information on the ticket before selecting it.
 - c. If an Assembly is selected, the default assembly split information will default into the bottom grid.
 - d. If a Farm is selected, the farm splits will default into the bottom grid.
5. Changing ownership on any selected Scale Tickets containing Purchase Contracts requires selecting **Remove Contracts from Selected Tickets**. This clears the contract(s) and applies the new contract information to the Scale Ticket.
6. Updating Scale Ticket information:
- An *Assembly #*, *Farm ID*, and *Field ID* can be changed on a Scale Ticket if the checkbox is selected.
 - If *Assembly #* is checked, the *Assembly #* must be for the same Commodity and Location.
 - If no information defaults in the grid or if the defaulted information needs changed, double-click *Customer ID* to select the Customer(s) of the new split arrangement.
 - *Share%*, *DPR*, *Contract*, *Shrink Schedule*, *Charge ID* (Storage/Service charge), *Drying Charge Schedule*, and *Freight Percent* can be changed for the split arrangement.
 - Changing the *Charge ID* (Storage/Service Charge schedule) removes any pre-existing charges.
7. Once split arrangement information is set, choose **Save** to update the Scale Ticket(s) selected.