

MyJohnDeere - SKY Dispatch

Last Modified on 12/09/2024 3:43 pm CST


Link and send VRT files to MyJohnDeere accounts from SKY Dispatch.

1. In SKY Admin, select **My John Deere Login** to navigate to the login page and sign into MyJohnDeere through SKY. This is available under the *Integrations Setup* area to enter a company-wide API Key and/or the *Location Preference Setup* to enter a Location-specific key.


Note: The Location key trumps the Company-level key when tying Vehicles to a Machine ID and when sending files.

Integrations Setup	Location Preference Setup
<input type="text" value="DriftWatch API Key"/>	<input type="text" value="Search Locations"/>
<input type="text" value="Navman Username"/>	<input type="text" value="00MAIN - SSI Farm Services - IL"/>
<input type="text" value="Navman Password"/>	<input type="checkbox"/> Show Product Detail in Grower Notification Emails
<input type="button" value="My John Deere Login"/>	<input type="button" value="My John Deere Login"/>
Not Logged In	Not Logged In


2. After selecting the **My John Deere Login** button, a popup will display to allow SKY Dispatch access to the John Deere Operations Center account.



3. Once access has been allowed, complete the setup of connections within John Deere Operations Center. Select an *Organization* and **Save**.



4. After selecting an *Organization*, edit *Access* to ensure this connection accesses all information needed for the integration. The *Equipment* setting must be a minimum of level 1 with the *Setup File Creator*, *Products*, and *Wireless Data Transfer* checkbox selected. The *Location* setting must be a minimum of level 3.




5. Once the connection setup is completed within John Deere Operations Center, return to SKY Dispatch to continue connecting John Deere devices to Agvance Vehicles.
6. MyJD Monitors can be tied to Agvance Vehicles in the *Integrations Setup* grid under *Company Settings* in SKY Dispatch. The name defaults into the *Machine Alias* area but can be edited.
7. On the *Jobs List* or *Map* view, after selecting the *Tickets*, the *More Options* menu gives the ability to *Send Files* to *MyJohnDeere*. Indicate the *Device to send files to* from the drop-down, then drag and drop or select **browse** to locate the appropriate zip file.

Upload Files

Devices to send files to

Please select files to upload

ACCEPTED FILES ARE: ZIP



Drag and drop here or [browse](#)

CancelUpload Files

8. When assigning a job in SKY Dispatch, the *Integration Type* tied to the Vehicle that is tied to the Applicator being assigned is shown in the drop-down.
9. Select **Files** at the bottom of the screen to view a queue of transferred files and their statuses. This grid includes the *Machine ID*, *Integration Type*, *File Name*, *Status*, and *Date Transferred*. *Last refreshed xx minute(s) ago* displays below the *Items per page* drop-down. Refreshing the browser window updates the number of minutes.
 - Common statuses and their meanings:
 - **In Process** – File has been sent to John Deere Operations Center.
 - **Success** – File was received by John Deere Operations Center.
 - **Available to Display** – File has been sent to device.
 - **Operator Accepted** – File has been downloaded to device by user.
 - **Operator Rejected** – User has deleted file prior to downloading to device.
 - **Queued** – File Received by John Deere Operations Center but device is offline.